

JOURNEYMAN GAME PLAY

HINTS AND TIPS

Q: How do I save the game?

A: Scroll to the Interface Bio-chip in the inventory window. Then click on the picture of the "Bio-chip Interface" and a panel comes up on the right. Press "Save Present" to save the game. Please save your game to your internal drive, or any drive other than the CD-ROM. Also, uniquely name each saved game so that you may restore the game at different points.

Q: How do I quit the game?

A: Press Command-Q or Command-period to quit (ESC or ALT + ESC on MPC).

Q: When I return from the Prehistoric to the Command Center and click on the left monitor it says "Please enter code on page 48." There is no page 48!

A: This was our way of telling you that time has changed! Ignore the left monitor, you cannot access it. Insert the log CD into the desk to access the right monitor.

Q: Can I copy the whole game to my 400+ MB Hard Drive?

A: Sure, all you have to do is drag the support files folder and the projectors to the top level of your hard drive and then rename your hard drive "Journeyman". Do not create a folder on your drive and put these files in it. Don't forget to eject the CD before playing.

Q: Is there a way to skip through the introductory animations?

A: Hit Command-M ("M" key on MPC) when the PRESTO logo starts to animate to get to the opening menu.

Q: My security codes don't work. It keeps saying "wrong code entered."

A: The repeat rate for the keystrokes is set too high. In your control panels, you will find a keyboard. Open it and set the "delay until repeat" to long and set the "key repeat rate" to slow. Tap in the code using the number pad on the keyboard. Wait between keypresses – don't go too fast. You should hear a tone after each quick keypress.

Q: In the Marx Maze, I keep running out of time.

A: If the computer is slow or the CD-ROM is slow, then you should use the keyboard for quicker response. If you need them, here are the exact directions for each intersection to leave the maze: L, R, R, L, L, go to the end then R, L, L, R, R, 1st R, L, R, jump in.

Q: In World Science Center I get hit by a dart and remove it, but I always die when I leave.

A: When you get hit by the dart you are drugged and must find a cure in the lab before leaving. Your goals are: analyze the dart, build the antidote, and synthesize the antidote. When you see a blue computer screen in front of you, click on it once or twice to activate the computer.

JOURNEYMAN

MPC TECHNICAL HELP – JOURNEYMAN

In addition to the notes listed below, more technical help can be found in the JMREADME.WRI file found on the Journeyman CD-ROM.

QUICKTIME ERRORS

Did you let the install modify AUTOEXEC.BAT?

NO Rerun the install and let it modify the AUTOEXEC.BAT.

Go to the DOS Prompt, type PATH, look for C:\QTW\BIN at the end of the path.

NOT FOUND Type EDIT AUTOEXEC.BAT and insert it at beginning of path. Make sure path is less than 128 characters.

Go to the DOS Prompt, type SET. Look for LIB=C:\QTW\LIB and INCLUDE=C:\QTW\INC.

NOT FOUND Type EDIT AUTOEXEC.BAT and add SET LIB=C:\QTW\LIB and SET INCLUDE=C:\QTW\INC on separate lines at the end.

Solution: Run the game with Quicktime in the background as follows:

Go into Windows. Double click on the Quicktime program group. Double click on Movie Player. With the Movie Player window up, press CTRL-ESC. Program Manager and Move Player should be the only tasks listed. END all others. Select PROGRAM MANAGER from the list and press the SWITCH TO button. Start the game normally.

GENERAL PROTECTION ERRORS

There is a problem with the Video Card or its drivers.

Are you playing the game in any mode except 640x480 – 256 colour mode?

YES Don't! Make sure you have the 640x480 – 256 drive for your Video Card (not the one that comes with Windows) selected under Windows set-up.

Do you have the latest version of the drivers for your Video Card?

NO Call your card manufacturer and get the latest drivers.

NOTE: ATI, STB and Orchid (Fahrenheit 1280 driver is bad) video cards are the most susceptible to this problem. Call Orchid for S3 flat model driver. That is the only solution for some cards.

SOUND PROBLEMS

Is your Sound Card a Sound Blaster?

NO Set it for Sound Blaster emulation. See your manual for details on how to do this.

Is your Sound Card a Pro Audio Spectrum 16 and the last word of each sentence gets cut off?

YES Call Media Vision and obtain the latest drivers.

GAME LOCKS UP FREQUENTLY

Is your Sound Card a Sound Blaster PRO?

YES Try setting the card to IRQ 5 vice IRQ 7. Also try setting the card to a DMA channel other than 1. Be careful to avoid conflicts with other cards in your machine.

TO BE AVOIDED

QEMM, PC Tools Shell, Norton Desktop Shell, Double Space, Stacker.